

December 2002 IC1031A

Installing USB 2.0 Drivers

Once the card is installed and the computer is restarted, Windows will detect the board and attempt to load the drivers for it.

Installing USB 2.0 drivers in Windows 98

- Windows will detect a "NEC USB Open Host Controller". Click "Next".
- Select "Search for the best driver for your device." Click "Next".
- When "Windows will search for new drivers in its driver database on your hard drive and in any of the following selected locations" dialog appears, uncheck all boxes. Click "Next".
- Windows has found an updated driver for this device. Click "Next". Then click "Next" again.
- The "Window has finished installing the software that your new hardware device requires" dialog appears. Click "Finish."
- After you have installed the NECUSB Open Host Controllers, Windows will find a "PCI Universal Serial Bus" device. Click "Next" to continue.
- Another dialog will appear. Select "Display a list of all the drivers in a specific location, so you can select the driver you want". Click "Next".
- In the dialog that appears, highlight "USB Controllers". Click "Next".
- Click on the "Have Disk" button.
- In the dialog that appears, click on the "Browse" button.
- Navigate to the folder that contains the USB 2.0 drivers. Click "OK".

- A dialog will appear with "NEC PCI to USB Enhanced Host Controller" highlighted, click "Next" to continue.
- The "Windows driver file search for the device" dialog appears with the location of the driver. Click "Next" to continue.
- The "Window has finished installing the software that your new hardware device requires" dialog appears. Click "Finish".
- Restart Windows.

Installing USB 2.0 Drivers in Window 2000

- Windows will find a "PCI Universal Serial Bus". Select "CD-ROM drivers". Click "Next".
- When "NEC PCI to USB Enhanced Host Controller" dialog appears, click "Next".
- The next dialog will let you know the driver has completed loading. Click "Finish" to finalize the installation. A "System Settings Change" dialog may appear, suggesting you "restart your computer now ".

Installing USB 2.0 Drivers in Window Me

- Windows will find a "PCI Universal Serial Bus". Select "Specify the location of the driver". Click "Next".
- Next windows will search for the best driver for your device. Check "Removable Media (Floppy, CD-ROM..) Click "Next".
- Navigate to the folder that contains the USB 2.0 drivers. Click "Next".
- When "NEC PCI to USB Enhanced Host Controller" dialog appears, click "Next" The next dialog will let you know the driver has completed loading. Click "Finish" to finalize the installation. A "System Settings Change" dialog may appear, suggesting you "restart your computer now".

© Copyright 2000. Black Box Corporation. All rights reserved.

1000 Park Drive * Lawrence, PA 15055-1018 * 724-746-5500 * Fax 724-746-0746

CUSTOMER SUPPORT INFORMATION Order toll-free in the U.S. 24 hours, 7 A.M. Monday to midnight Friday: 877-877-BBOX FREE technical support, 24 hours a day, 7 days a week: Call 724-746-5500 or fax 724-746-0746 Mail order: Black Box Corporation, 1000 Park Drive, Lawrence, PA 15055-1018 Web site: www.blackbox.com • E-mail: info@blackbox.com